# Stony Brook University MAT 118 Spring 2013 Arithmetic with binary numbers

We take our decimal place-value notation for granted. But it only came to the West with Fibonacci around 1200 AD, and was slow to be adopted. Galileo (1564-1642) was a master of arithmetic but never wrote a decimal point, as far as we know. Binary arithmetic, besides giving insight into how computers process numbers, shows by a second example the power of placevalue notation.

#### What are binary numbers

In decimal notation each digit (0, 1, 2, 3, 4, 5, 6, 7, 8, 9) represents a multiple of a power of 10. Which power it is depends on the *place*. Just looking at whole numbers for the moment, the rightmost digit is units (multiples of  $1 = 10^{0}$ ). Moving to the left the next digit represents tens (multiples of  $10 = 10^{1}$ ), the next is hundreds (multiples of  $100 = 10^{2}$ ) and so on. So  $327 = 3 \times 10^{2} + 2 \times 10^{1} + 7 \times 10^{0} = 300 + 20 + 7$ , etc.

Binary notation works exactly the same, except that each digit (0, 1) represents a multiple of a power of 2. The power depends on the place exactly as in decimal notation. When it's necessary to distinguish binary digits from decimal we can use subscripts 2 or 10 to tell them apart. So for example  $101101_2 = 1 \times 2^5 + 0 \times 2^4 + 1 \times 2^3 + 1 \times 2^2 + 0 \times 2^1 + 1 \times 2^0 = 32_{10} + 8_{10} + 4_{10} + 1 = 45_{10}$ .

## Conversion from decimal to binary

There are two standard ways to convert a decimal into binary. The most simple-minded is to look for the largest power of 2 which is less than or equal to the given number. Subtract that power from your number. Then look for the largest power of 2 which is less than or equal to the difference. Subtract that power and repeat until you are left with 0 or 1. Then you will have expressed your number as a sum of powers of 2, which tells you where to put the 1s in its binary representation. For example, to convert  $81_{10}$  into binary: The largest power of 2 in 81 is  $64 = 2^6$ . The difference is 81 - 64 = 17. The largest power of 2 in 17 is  $16 = 2^4$ . The difference is 17 - 16 = 1 so we can stop. We now know  $81 = 64 + 16 + 1 = 2^6 + 2^4 + 2^0$ . So  $81_{10} = 1010001_2$ .

## Addition

Addition is performed by stacking the numbers to be added vertically such that the binary places match. Then the digits are added column by column, with carries as usual. Note the carries in this example, which corresponds to the decimal 27 + 13 = 40:

	1	1	1	1	
	1	1	0	1	1
+		1	1	0	1
1	0	1	0	0	0

In the next example, which corresponds to 27 + 29 + 5 + 15 = 76, the first column sums to binary 100, so a 1 gets carried into the *third* column. Etc.

		1		1		
		1		1		
		1	1	0	1	1
		1	1	1	0	1
				1	0	1
+			1	1	1	1
1	0	0	1	1	0	0

## Subtraction

Subtraction is performed exploiting our place-value notation by writing the number to be subtracted below the larger number, with places lined up, and working column by column from the right, as usual, with borrowing when necessary.

In this example, the borrowings are written small, and what's left after the borrowing is written regular size. This corresponds to 46 - 27 = 19 in decimal notation. Note that after you have borrowed from your neighbor, he needs to borrow to cover his debit.

	0			0	$^{1}0$	
	1	<b>1</b> 0	1	1	1	<b>1</b> 0
_		1	1	0	1	1
		1	0	0	1	1

In the next example, which corresponds to 44 - 27 = 17, your neighbor has to borrow so you can borrow from him. Your neighbor now has two (10) so when you borrow one from him, he has 1 left over.

## Multiplication

Let's start small. These examples are chosen so that the addition part does not involve complicated carries.

		1	0	1
	×	1	0	1
		1	0	1
	0	0	0	
1	0	1		
1	1	0	0	1

As usual we won't write in a row of 0s, but just put a zero at the righthand end of the next line (this calculation is the decimal  $5 \times 5 = 25$ ):

		1	0	1
	×	1	0	1
		1	0	1
1	0	1	0	
1	1	0	0	1

Here is  $54 \times 9 = 486$  in binary:

			1	1	0	1	1	0
				×	1	0	0	1
			1	1	0	1	1	0
1	1	0	1	1	0	0	0	
1	1	1	1	0	0	1	1	0

## Division

We do it just like regular long division. It's easier because at each step either the divisor is less than the current dividend, producing a 1, or it is smaller, producing a 0. To learn this technique it is essential to work the examples yourself, in pencil, along with the calculations in these notes. Here is  $86 \div 3 = 28$ , remainder 2:

$$\begin{array}{r} 11100\\ 11 \overline{)1010110}\\ \underline{11}\\ 100\\ \underline{11}\\ 110\\ \underline{11}\\ 11\\ \underline{11}\\ 010 \end{array}$$

And here is  $94 \div 5 = 18$ , remainder 4. (I cribbed the TeX-code for these examples from the web).

1001	0
$101 \overline{)101111}$	0
101	
0111	
101	
10	0

And here is  $1750 \div 26 = 67$ , remainder 8.

]	1000011
11010)11011	1010110
11010	)
]	101011
	11010
-	100010
	11010
	1000